

alfaview

Developer Handbook



support.alfaview.com

March 13, 2026

Contents

Command line options	2
Legal Notice	4

Command line options

Source: <https://support.alfaview.com/en/developers/command-line-options/>

Command	Usage
<code>--allowmultiple</code>	This command allows you to run multiple alfaview instances simultaneously on Windows and Linux operating systems. Note: This command does not work if you join an alfaview room using an invitation link.
<code>--autoacceptwelcome</code>	This command prevents the accessibility settings, general settings as well as audio and video settings from being set up before joining an alfaview room for the first time. Changes to these settings can be made in the app or via the webclient later on.
<code>--bypasssettings</code>	This command prevents the saved settings from being applied. Instead, alfaview opens with the default settings. Any settings made during this session are not saved.
<code>--disableleaveroom</code>	This command prevents users from leaving the alfaview room and returning to the login page or the room and meeting list. The Leave room icon is not displayed to users in the alfaview room.
<code>--help</code>	This command displays all available help information.
<code>--loglevel</code>	This command can be used to output log entries by level. Valid values are: <code>debug / info / warning / error / critical</code> . The command value <code>--loglevel=debug</code> corresponds to the command <code>--verbose</code> . Note: You will receive all log entries of the level <code>info</code> (default) until the level you set is set by the alfaview application.
<code>--nocolor</code>	This command deactivates the coloring in the command center terminal.

Command	Usage
<code>--noupdate</code>	This command prevents alfaview from automatically checking for new updates. Note: Update alfaview regularly. Older alfaview versions are gradually excluded from usage.
<code>--skipportcheck</code>	This command prevents alfaview from checking ports and determining whether a connection can be established. alfaview is launched directly. We do not recommend this command if it is not absolutely necessary.
<code>--skipquicksetup</code>	This command deactivates the Quick settings before a user joins an alfaview room. Instead, the user will directly join the alfaview room, where they can adjust the settings.
<code>--url</code>	This command is automatically set for invitation links. It opens the alfaview room for which the join permission has been granted. For an example usage, please refer to page Generate join url from group link [?] .
<code>--verbose</code>	This command activates the extended debug logging (more details).
<code>--version</code>	This command displays the alfaview version currently in use.

Last updated on March 21st, 2025, 09:13 am

Legal Notice

Publisher

alfaview GmbH

Kriegsstr. 100
76133 Karlsruhe, Germany

Website: www.alfaview.com

Email: info@alfaview.com

Phone: +49 721 35450-450

Fax: +49 721 35450-69

Managing Director: Nikolaos Fostiropoulos

Court Registration: District court Mannheim HRB 730903

VAT ID: DE318911962

Technical Service Provider

alfatraining Bildungszentrum GmbH

Kriegsstraße 100
76133 Karlsruhe, Germany

Managing Director: Nikolaos Fostiropoulos

Court Registration: District court Mannheim HRB 730739

VAT ID: DE318522740

Copyright

The website design is protected by copyright. All images on this website are protected by copyright. The downloading of pictures, their further publication, further transmission, reproduction or other use is prohibited.

Dispute Resolution

The European Commission provides an Online Dispute Resolution platform at <https://ec.europa.eu/consumers/odr>. *alfaview* GmbH does not participate in consumer arbitration procedures.